


Configuration steps for TensorFlow object detection-



STEP-1 Download the following content-


1. [Download](#) v1.13.0 model.
2. [Download](#) the `ssd_mobilenet_v1_coco` model from the model zoo or any other model of your choice from [TensorFlow 1 Detection Model Zoo](#).
3. [Download](#) Dataset & utils.
4. [Download](#) labellmg tool for labeling images.

before extraction, you should have the following compressed files -



STEP-2 Extract all the above zip files into a tfod folder and remove the compressed files-

Now you should have the following folders -



STEP-3 Creating virtual env using conda-



STEP-4 Install the following packages in your new environment-

for GPU

```
pip install pillow lxml Cython contextlib2 jupyter matplotlib pandas opencv-python tensorflow-gpu==1.15.0
```

for CPU only

```
pip install pillow lxml Cython contextlib2 jupyter matplotlib pandas opencv-python tensorflow==1.15.0
```

STEP-5 Install protobuf using conda package manager-

```
conda install -c anaconda protobuf
```

STEP-6 For protobuf to .py conversion download from a tool from here-

For windows -> [download](#) source for other versions and OS - [click here](#)

Open command prompt and cd to research folder.

Now in the research folder run the following command-

For Linux or Mac


```
protoc object_detection/protos/*.proto --python_out=.
```

For Windows

```
protoc object_detection/protos/*.proto --python_out=.
```

STEP-7 Paste all content present in utils into research folder-

Following are the files and folder present in the utils folder-



STEP-8 Paste ssd_mobilenet_v1_coco or any other model downloaded from model zoo into research folder-

Now cd to the research folder and run the following python file-

```
python xml_to_csv.py
```


STEP-9 Run the following to generate train and test records-

from the research folder-


```
python generate_tfrecord.py --csv_input=images/train_labels.csv --image_dir=images/train --output_path=train.record
```

```
python generate_tfrecord.py --csv_input=images/test_labels.csv --image_dir=images/test --output_path=test.record
```

STEP-10 Copy from `research/object_detection/samples/config/ YOURMODEL.config` file into `research/training-`



STEP-11 Update `num_classes`, `fine_tune_checkpoint`, and `num_steps` plus update `input_path` and `label_map_path` for both `train_input_reader` and `eval_input_reader`-




Click here to see the full config file

```
1 # SSDLite with Mobilenet v1 configuration for MSCOCO Dataset.
2 # Users should configure the fine_tune_checkpoint field in the train config as
3 # well as the label_map_path and input_path fields in the train_input_reader and
4 # eval_input_reader. Search for "PATH_TO_BE_CONFIGURED" to find the fields that
5 # should be configured.
6
7 model {
8   ssd {
9     num_classes: 6
10    box_coder {
11      faster_rcnn_box_coder {
12        y_scale: 10.0
13        x_scale: 10.0
14        height_scale: 5.0
15        width_scale: 5.0
16      }
17    }
18    matcher {
19      argmax_matcher {
20        matched_threshold: 0.5
21        unmatched_threshold: 0.5
22        ignore_thresholds: false
23        negatives_lower_than_unmatched: true
24        force_match_for_each_row: true
25      }
26    }
27    similarity_calculator {
28      iou_similarity {
29      }
30    }
31    anchor_generator {
32      ssd_anchor_generator {
33        num_layers: 6
34        min_scale: 0.2
35        max_scale: 0.95
36        aspect_ratios: 1.0
37        aspect_ratios: 2.0
38        aspect_ratios: 0.5
39        aspect_ratios: 3.0
40        aspect_ratios: 0.3333
41      }
42    }
43    image_resizer {
44      fixed_shape_resizer {
45        height: 300
46        width: 300
47      }
48    }
49    box_predictor {
50      convolutional_box_predictor {
51        min_depth: 0
52        max_depth: 0
53        num_layers_before_predictor: 0
54        use_dropout: false
55        dropout_keep_probability: 0.8
56        kernel_size: 3
57        use_depthwise: true
58        box_code_size: 4
59        apply_sigmoid_to_scores: false
60        conv_hyperparams {
61          activation: RELU_6,
62          regularizer {
63            l2_regularizer {
64              weight: 0.00004
65            }
66          }
67          initializer {
68            truncated_normal_initializer {
69              stddev: 0.03
70              mean: 0.0
71            }
72          }
73          batch_norm {
74            train: true,
75            scale: true,
76            center: true,
77            decay: 0.9997,
78            epsilon: 0.001,
79          }
80        }
81      }
82    }
83    feature_extractor {
84      type: 'ssd_mobilenet_v1'
85      min_depth: 16
86      depth_multiplier: 1.0
87      use_depthwise: true
88      conv_hyperparams {
89        activation: RELU_6,
90        regularizer {
91          l2_regularizer {
92            weight: 0.00004
93          }
94        }
95        initializer {
96          truncated_normal_initializer {
97            stddev: 0.03
98            mean: 0.0
99          }
100        }
101        batch_norm {
102          train: true,
103          scale: true,
104          center: true,
105          decay: 0.9997,
106          epsilon: 0.001,
107        }
108      }
109    }
110    loss {
111      classification_loss {
112        weighted_sigmoid {
113        }
114      }
115      localization_loss {
116        weighted_smooth_l1 {
117        }
118      }
119      hard_example_miner {
120        num_hard_examples: 3000
121        iou_threshold: 0.99
122        loss_type: CLASSIFICATION
123        max_negatives_per_positive: 3
124        min_negatives_per_image: 0
125      }
126      classification_weight: 1.0
127      localization_weight: 1.0
128    }
129    normalize_loss_by_num_matches: true
130    post_processing {
131      batch_non_max_suppression {
132        score_threshold: 1e-8
133        iou_threshold: 0.6
134        max_detections_per_class: 100
135        max_total_detections: 100
136      }
137      score_converter: SIGMOID
138    }
139  }
140 }
141
142 train_config {
143   batch_size: 24
144   optimizer {
145     rms_prop_optimizer {
146       learning_rate {
147         exponential_decay_learning_rate {
148           initial_learning_rate: 0.004
149           decay_steps: 800720
150           decay_factor: 0.95
151         }
152       }
153       momentum_optimizer_value: 0.9
154       decay: 0.9
155       epsilon: 1.0
156     }
157   }
158   fine_tune_checkpoint: "ssd_mobilenet_v1_coco_2018_01_28/model.ckpt"
159   from_detection_checkpoint: true
160   # Note: The below line limits the training process to 200K steps, which we
161   # empirically found to be sufficient enough to train the pets dataset. This
162   # effectively bypasses the learning rate schedule (the learning rate will
163   # never decay). Remove the below line to train indefinitely.
164   num_steps: 200000
165   data_augmentation_options {
166     random_horizontal_flip {
167     }
168   }
169   data_augmentation_options {
170     ssd_random_crop {
171     }
172   }
173 }
174
175 train_input_reader {
176   tf_record_input_reader {
177     input_path: "train.record"
178   }
179   label_map_path: "training/labelmap.pbtxt"
180 }
181
182 eval_config {
183   num_examples: 8000
184   # Note: The below line limits the evaluation process to 10 evaluations.
185   # Remove the below line to evaluate indefinitely.
186   max_evals: 10
187 }
188
189 eval_input_reader {
190   tf_record_input_reader {
191     input_path: "test.record"
192   }
193   label_map_path: "training/labelmap.pbtxt"
194   shuffle: false
195   num_readers: 1
196 }
```


STEP-12 From *research/object_detection/legacy/* copy *train.py* to research folder

legacy folder contains train.py as shown below -



STEP-13 Copy *deployment* and *nets* folder from *research/slim* into the *research* folder-

slim folder contains the following folders -



STEP-14 NOW Run the following command from the *research* folder. This will start the training in your *local system*-

Note

copy the command and replace **YOUR_MODEL.config** with your own model's name for example **ssd_mobilenet_v1_coco.config** and then run it in cmd prompt or terminal. And make sure you are in *research* folder.

python train.py --logtostderr --train_dir=training/ --pipeline_config_path=training/YOUR_MODEL.config

Warning

Always run all the commands in the research folder.